

NFS

NFS NFS NFS

```
+-----+ | +-----+
| [NFS   ] | 10.0.0.30 | 10.0.0.51 | [NFS   ] |
| dlp.srv.world +-----+ node01.srv.world |
| | | |
+-----+ +-----+
```

[1] NFS

```
[root@node01 ~]# dnf -y install nfs-utils
[root@node01 ~]# vi /etc/idmapd.conf
# line 5 : uncomment and change to your domain name
Domain = srv.world
[root@node01 ~]# mount -t nfs dlp.srv.world:/home/nfsshare /mnt
[root@node01 ~]# df -hT
```

Filesystem	Type	Size	Used	Avail	Use%	Mounted on
devtmpfs	devtmpfs	1.9G	0	1.9G	0%	/dev
tmpfs	tmpfs	1.9G	0	1.9G	0%	/dev/shm
tmpfs	tmpfs	1.9G	8.6M	1.9G	1%	/run
tmpfs	tmpfs	1.9G	0	1.9G	0%	/sys/fs/cgroup
/dev/mapper/cs-root	xfs	26G	2.3G	24G	9%	/
/dev/vda1	xfs	1014M	259M	756M	26%	/boot
tmpfs	tmpfs	374M	0	374M	0%	/run/user/0
dlp.srv.world:/home/nfsshare	nfs4	26G	2.3G	24G	9%	/mnt

```
# NFS share is mounted

# if mount with NFSv3, add [-o vers=3] option
[root@node01 ~]# mount -t nfs -o vers=3 dlp.srv.world:/home/nfsshare /mnt
[root@node01 ~]# df -hT /mnt
```

Filesystem	Type	Size	Used	Avail	Use%	Mounted on
dlp.srv.world:/home/nfsshare	nfs	26G	2.3G	24G	9%	/mnt

[2] [/etc/fstab]

```
[root@node01 ~]# vi /etc/fstab
```

/dev/mapper/cs-root	/	xfs	defaults	0 0
UUID=72e65d16-7d1a-40bc-9bc1-e45a8ba6d084 /boot xfs defaults 0 0				
/dev/mapper/cs-swap	none	swap	defaults	0 0
# add to the end : set NFS share				
dlp.srv.world: /home/nfsshare	/mnt	nfs	defaults	0 0

[3] NFS AutoFS

```
[root@node01 ~]# dnf -y install autofs
[root@node01 ~]# vi /etc/auto.master
# add to the end
/- /etc/auto.mount

[root@node01 ~]# vi /etc/auto.mount
# create new : [mount point] [option] [location]
/mnt -fstype=nfs,rw dlp.srv.world: /home/nfsshare

[root@node01 ~]# systemctl enable --now autofs
# move to the mount point to verify mounting
[root@node01 ~]# cd /mnt
[root@node01 mnt]# ll
total 8
-rw-r--r--. 1 root root 10 Mar  3 19:14 testfile.txt
-rw-r--r--. 1 root root  5 Mar  3 19:17 test.txt

[root@node01 mnt]# grep /mnt /proc/mounts
/etc/auto.mount /mnt autofs
rw,relatime,fd=17,pgrp=2468,timeout=300,minproto=5,maxproto=5,direct,pipe_ino=33352 0 0
dlp.srv.world: /home/nfsshare /mnt nfs4
rw,relatime,vers=4.2,rsiz=1048576,wsiz=1048576,namlen=255,hard,proto=tcp,timeo=600,retrans=2
,sec=sys,clientaddr=10.0.0.51,local_lock=none,addr=10.0.0.30 0 0
```

Revision #1

Created 23 July 2022 19:56:26 by

Updated 23 July 2022 19:59:37 by